

BCM - User Option

Tested Model: KIA Sorento (MQ4) 2025

Supported Equipment: Launch PRO or PAD series
comprehensive diagnostic equipment

Function Description:


1. This function allows users to adjust factory-reserved personalized configurable parameters within the BCM (Body Control Module). It does not modify core powertrain programs and only adapts to the owner's usage habits.



Attention:

1. Select the item to modify.
2. Select the value from the combo box.
3. The "User Option" menu varies by vehicle model.


Procedure:

1. On a PRO3S+, choose [Local Diagnose], and then choose [KIA] for testing.







2. Choose [Automatically Search] to identify the vehicle model.




3. Confirm the vehicle information, and then click "OK".




4. Choose [BDC (Body Domain Controller)-BCM (Body Control Module)] to enter it.




5. Choose [Special function].



6. Choose [User Option].



7. Read the on-screen prompts regarding data writing for this function, and then click "OK" to proceed with item operations.



8. Click the corresponding item according to requirements, and choose [Enable] after entering that item.

Special Function

KIA V46.60 > Automatically Search > General Area > Sorento(MQ4) > 2025 > D 2.2 TCI New R > BDC(Body Domain Controller)-... 12.01V

Item	Value
RK Trunk Button Function Lock	Disable
Wiper Interlocking Head Lamp	Disable
Wiper User Option Setting	Disable

Cancel OK

SN:
KIA Sorento(MQ4) 2025
VIN

Show Menu

KIA V46.60 > Automatically Search > General Area > Sorento(MQ4) > 2025 > D 2.2 TCI New R > BDC(Body Domain Controller)-... 12.01V


Q Please enter keyword

Disable

Enable

SN:
KIA Sorento(MQ4) 2025
VIN

9. After enabling the selected item, click "OK" on the selection screen to apply the configuration change.



Statement:

The content of this document is copyrighted by LAUNCH TECH CO., LTD., and no individual or organization may quote or reprint it without consent.